

17. Mohr Circle for Traction

- I Main Topics
 - A Stresses vs. tractions
 - B Mohr circle for tractions
 - C Example


10/19/16

GG303

1

17. Mohr Circle for Traction

- From King et al., 1994 (Fig. 11)
- Coulomb stress change caused by the Landers rupture. The left-lateral ML=6.5 Big Bear rupture occurred along dotted line 3 hr 26 min after the Landers main shock. The Coulomb stress increase at the future Big Bear epicenter is 2.2-2.9 bars.



10/19/16

GG303


2

17. Mohr Circle for Traction

II Stresses vs. tractions

A Similarities between stresses and tractions

- 1 Same dimensions (force per unit area)
- 2 The normal stress acting on a plane matches the normal traction




Note the use of double subscripts here on the tractions; This unconventional

17. Mohr Circle for Traction

II Stresses vs. tractions (cont.)

B Differences between stresses and tractions

- 1 Stresses are tensor quantities and tractions are vectors.
- 2 The stress state is defined at a point using a fixed reference frame, whereas a traction is defined on a plane with a reference frame that floats with the plane.
- 3 Shear stress components on perpendicular planes have the same sign, whereas shear tractions on perpendicular planes have opposite signs.



17. Mohr Circle for Traction

III Mohr circle for tractions


A $\tau_n = \sigma_1 \cos^2 \theta + \sigma_2 \sin^2 \theta$

B $\tau_s = (\sigma_2 - \sigma_1) \sin \theta \cos \theta$

Now $\cos^2 \theta = (1/2)(1 + \cos 2\theta)$
 $\sin^2 \theta = (1/2)(1 - \cos 2\theta)$
 $\sin \theta \cos \theta = (1/2)(\sin 2\theta)$

C $\tau_n = \frac{\sigma_1 + \sigma_2}{2} + \frac{\sigma_1 - \sigma_2}{2} \cos 2\theta$

D $\tau_s = \frac{-(\sigma_1 - \sigma_2)}{2} \sin 2\theta$



17. Mohr Circle for Traction

III Mohr circle for tractions


C $\tau_n = \frac{\sigma_1 + \sigma_2}{2} + \frac{\sigma_1 - \sigma_2}{2} \cos 2\theta$

D $\tau_s = \frac{-(\sigma_1 - \sigma_2)}{2} \sin 2\theta$

Now $c = \frac{\sigma_1 + \sigma_2}{2}$ $r = \frac{\sigma_1 - \sigma_2}{2}$

E $\tau_n = c + r \cos(-2\theta)$


F $\tau_s = r \sin(-2\theta)$



Equations of a Mohr circle for tractions
 Relate tractions on planes of different orientation
 c is mean normal stress (traction)
 r is maximum shear traction (the circle radius)
 σ_1 is the most tensile stress
 σ_2 is the least tensile stress

17. Mohr Circle for Traction

FORCE BALANCE DIAGRAM
("Physical space")



CORRESPONDING MOHR CIRCLE
("Mohr circle space")





Fig. 17.1

G Key points

- 1 $\theta = \theta_{1n}$ is the angle between the normal to the plane σ_1 acts on and the normal to the plane of interest
- 2 If positive θ is counterclockwise in "physical space", -2θ is clockwise in "Mohr circle space"

17. Mohr Circle for Traction



Stresses Traction

σ_{xx}	+10 MPa	τ_{xn}	+10 MPa
σ_{xy}	+3 MPa	τ_{xs}	+3 MPa
σ_{yx}	+3 MPa	τ_{ys}	-3 MPa
σ_{yy}	+2 MPa	τ_{yn}	+2 MPa


Note that the magnitude of the normal stresses and normal tractions are equal. So $\tau_1 = \sigma_1$ below.

Example 1 using Mohr circle to find principal stresses


- Suppose $\sigma_{xx} = +10$ MPa (tension), $\sigma_{yy} = +2$ MPa (tension), and $\sigma_{xy} = +3$ MPa (left lateral shear), and $\sigma_{yx} = +3$ MPa (right lateral shear).

- A) Draw a box in a reference frame and clearly label the stresses on its sides; this is a critically important step.
- B) Determine the stresses and tractions on the faces of the box. Here, we use the tensor "on-in" convention.

17. Mohr Circle for Traction



Here, $-2\theta_{xx'} = -37^\circ$ (clockwise), so $\theta_{xx'} = +18.5^\circ$ (counterclockwise)



- C Plot and label the points on a set of labelled τ_n , τ_s axes.
- D Draw the Mohr circle through the points by finding the center (c) and radius (r) of the circle.
- E Label the principal magnitudes τ_1 and τ_2 ($\tau_1 > \tau_2$); they come from the intersection of the circle with the normal stress (τ_n) axis.
- F Assign reference axes to the principal directions; I chose x' for the τ_1 -direction.
- G Label the negative double angle between the traction pair that act on a plane with a known normal direction (here, x or y) and the traction pair that act on a plane with an unknown direction (e.g., x').
- H Draw and label a new reference frame and box showing the principal stresses, making sure to use the double angle relationship correctly.