- I Main Topics
 - A General solution for a plane strain case
 - **B** Boundary conditions
 - C Solution that honors boundary conditions
 - D Significance of solution
 - E Superposition
 - **F** Stress concentrations

Ship Rock, New Mexico



http://jencarta.com/images/aerial/ShipRock.jpg

Hydraulic Fracture



From Wu et al., 2007

10/10/18 GG303 2

II General solution for a plane strain case Start with the governing equation

$$0 = \frac{d^2 u_r}{dr^2} + \frac{1}{r} \frac{du_r}{dr} - \frac{u_r}{r^2}$$

Consider a power series solution for u_r and its derivatives

$$u_r = \dots$$
 $C_{-3}r^{-3} + C_{-2}r^{-2} + C_{-1}r^{-1} + C_0r^0 + C_1r^1 + C_2r^2 + C_3r^3 + \dots$

$$\frac{du_r}{dr} = \dots -3C_{-3}r^{-4} - 2C_{-2}r^{-3} - 1C_{-1}r^{-2} + 0C_0r^{-1} + 1C_1r^0 + 2C_2r^1 + 3C_3r^2 + \dots$$

$$\frac{d^2 u_r}{dr^2} = \dots \ 12C_{-3}r^{-5} + 6C_{-2}r^{-4} + 2C_{-1}r^{-3} + 0C_0r^{-2} + 0C_1r^{-1} + 2C_2r^0 + 6C_2r^1 \dots$$

10/10/18

II General Solution for a plane strain case

Now substitute the series solutions into the governing equation $0 = \frac{d^2 u_r}{dr^2} + \frac{1}{r} \frac{du_r}{dr} - \frac{1}{r^2} u_r$

$$0 = \dots 12C_{-3}r^{-5} + 6C_{-2}r^{-4} + 2C_{-1}r^{-3} + 0C_{0}r^{-2} + 0C_{1}r^{-1} + 2C_{2}r^{0} + 6C_{3}r^{1} \dots$$

$$+ \frac{1}{r} \Big(\dots - 3C_{-3}r^{-4} - 2C_{-2}r^{-3} - 1C_{-1}r^{-2} + 0C_{0}r^{-1} + 1C_{1}r^{0} + 2C_{2}r^{1} + 3C_{3}r^{2} + \dots \Big)$$

$$- \frac{1}{r^{2}} \Big(\dots C_{-3}r^{-3} + C_{-2}r^{-2} + C_{-1}r^{-1} + C_{0}r^{0} + C_{1}r^{1} + C_{2}r^{2} + C_{3}r^{3} + \dots \Big)$$

$$0 = \dots \qquad 12C_{-3}r^{-5} + 6C_{-2}r^{-4} + 2C_{-1}r^{-3} + 0C_{0}r^{-2} + 0C_{1}r^{-1} + 2C_{2}r^{0} + 6C_{3}r^{1} + \dots$$

$$+ (\dots - 3C_{-3}r^{-5} - 2C_{-2}r^{-4} - 1C_{-1}r^{-3} + 0C_{0}r^{-2} + 1C_{1}r^{-1} + 2C_{2}r^{0} + 3C_{3}r^{1} + \dots)$$

$$- (\dots \quad C_{-3}r^{-5} + C_{-2}r^{-4} + C_{-1}r^{-3} + C_{0}r^{-2} + C_{1}r^{-1} + C_{2}r^{0} + C_{3}r^{1} + \dots)$$

10/10/18

II General Solution for a plane strain case

$$0 = \dots 12C_{-3}r^{-5} + 6C_{-2}r^{-4} + 2C_{-1}r^{-3} + 0C_{0}r^{-2} + 0C_{1}r^{-1} + 2C_{2}r^{0} + 6C_{3}r^{1} + \dots$$

$$+ (\dots -3C_{-3}r^{-5} - 2C_{-2}r^{-4} - 1C_{-1}r^{-3} + 0C_{0}r^{-2} + 1C_{1}r^{-1} + 2C_{2}r^{0} + 3C_{3}r^{1} + \dots)$$

$$+ (\dots -1C_{-3}r^{-5} - 1C_{-2}r^{-4} - 1C_{-1}r^{-3} - 1C_{0}r^{-2} - 1C_{1}r^{-1} - 1C_{2}r^{0} - 1C_{3}r^{1} - \dots)$$

Now collect terms of the same powers

$$0 = \dots 8C_{-3}r^{-5} + 3C_{-2}r^{-4} + 0C_{-1}r^{-3} - 1C_{0}r^{-2} + 0C_{1}r^{-1} + 3C_{2}r^{0} + 8C_{3}r^{1} + \dots$$

II General Solution for a plane strain case

$$0 = \dots 8C_{-3}r^{-5} + 3C_{-2}r^{-4} + 0C_{-1}r^{-3} - 1C_0r^{-2} + 0C_1r^{-1} + 3C_2r^{0} + 8C_3r^{1} + \dots$$

For this to hold for *all* values of r, the product of each leading coefficient and constant must equal 0 because the powers of r are linearly independent. *All* coefficients *except* C_{-1} and C_1 thus must be zero.

$$u_r = \dots C_{-3}r^{-3} + C_{-2}r^{-2} + C_{-1}r^{-1} + C_0r^0 + C_1r^1 + C_2r^2 + C_3r^3 + \dots$$


$$u_r = C_{-1}r^{-1} + C_1r^1$$

- General solution for radial displacements
- Solve for constants via boundary conditions

III Boundary conditions

A Two boundary conditions must be specified to solve our problem because our general solution has two unknown coefficients:


$$u_r = C_{-1}r^{-1} + C_1r^1$$



III Boundary conditions: Radial displacements

> B $u_r = u_0$ at the wall of the hole: $u_r|_{r=a} = u_0$

C $u_r = 0$ at infinity: $u_r|_{r=b=\infty} = 0$




IV Solution that honors boundary conditions

Gov. eq.:
$$u_r = C_{-1}r^{-1} + C_1r^1$$

BC 1:
$$u_r|_{r=a} = u_0$$

BC 2:
$$u_r|_{r=b=\infty} = 0$$

As
$$r \rightarrow \infty$$
, $u_r \rightarrow C_1 r$
BC 2 requires $C_1 = 0$, so $u_r = C_{-1} r^{-1}$



IV Solution that honors boundary conditions

Gov. eq.:
$$u_r = C_{-1}r^{-1} + C_1r^1$$

BC 1:
$$u_r|_{r=a} = u_0$$

BC 2:
$$u_r|_{r=b=\infty} = 0$$

As
$$r \rightarrow \infty$$
, $u_r \rightarrow C_1 r$


BC 2 requires
$$C_1 = 0$$
, so

$$u_r = C_{-1}r^{-1}$$

By BC 1,
$$u_r|_{r=a} = u_0 = C_{-1}a^{-1}$$

So, $C_{-1} = a u_0$

$$u_r = (a/r) u_0$$




Solution satisfying boundary conditions

IV Solution that honors boundary conditions (cont.)

$$u_r = (a/r) u_0$$

- The hole radius a provides a scale
- The displacements decay with distance r from the hole (as suspected)
- The displacements scale with u_0
- Problems with different boundary conditions have different solutions




IV Solution that honors boundary conditions (cont.)

Strains

$$\varepsilon_{rr} = \frac{\partial u_r}{\partial r} = \frac{\partial \left(u_0 a r^{-1}\right)}{\partial r} = u_0 a \frac{\partial \left(r^{-1}\right)}{\partial r}$$
$$= \frac{-u_0 a}{r^2} = -u_0 a r^{-2}$$

$$\varepsilon_{\theta\theta} = \frac{u_r}{r} = \frac{u_0 a r^{-1}}{r} = \frac{u_0 a}{r^2} = u_0 a r^{-2}$$



$$\varepsilon_{r\theta} = 0$$

IV Solution that honors boundary conditions (cont.)

Stresses (in terms of u₀)

$$\underline{\sigma_{rr}} = \frac{E}{(1+v)} \left[\varepsilon_{rr} + \frac{v}{(1-2v)} (\varepsilon_{rr} + \varepsilon_{\theta\theta}) \right]$$

$$= \frac{E}{(1+v)} \left[\frac{-u_0 a}{r^2} + \frac{v}{(1-2v)} \left(\frac{-u_0 a}{r^2} + \frac{u_0 a}{r^2} \right) \right]$$

$$= \frac{E}{(1+v)} \left[\frac{-u_0 a}{r^2} \right]$$

Strains Ur

IV Solution that honors boundary conditions (cont.)

Stresses (in terms of u₀)

$$\underline{\sigma_{rr}} = \frac{E}{(1+v)} \left[\varepsilon_{rr} + \frac{v}{(1-2v)} \left(\varepsilon_{rr} + \varepsilon_{\theta\theta} \right) \right]$$
 Strains
$$= \frac{E}{(1+v)} \left[\frac{-u_0 a}{r^2} + \frac{v}{(1-2v)} \left(\frac{-u_0 a}{r^2} + \frac{u_0 a}{r^2} \right) \right]$$

$$= \frac{E}{(1+v)} \left[\frac{-u_0 a}{r^2} \right]$$

$$\underline{\sigma_{\theta\theta}} = \frac{E}{(1+v)} \left[\varepsilon_{\theta\theta} + \frac{v}{(1-2v)} \left(\varepsilon_{\theta\theta} + \varepsilon_{rr} \right) \right]$$

$$= \frac{E}{(1+v)} \left[\frac{u_0 a}{r^2} + \frac{v}{(1-2v)} \left(\frac{u_0 a}{r^2} + \frac{-u_0 a}{r^2} \right) \right]$$

$$= \frac{E}{(1+v)} \left[\frac{u_0 a}{r^2} \right]$$

Strains ur

Same absolute magnitude, opposite sign; $\sigma_{rr} = -\sigma_{\theta\theta}$

$$\sigma_{r\theta} = 2G\varepsilon_{r\theta} = 0$$

IV Solution that honors boundary conditions (cont.)

Stresses (in terms of tractions)

First evaluate the radial stress on the wall of the hole (r=a), which equals traction T, and from that solve for u_0


$$\sigma_{rr}\big|_{r=a} = \frac{E}{(1+v)} \left[\frac{-u_0 a}{a^2} \right] = \frac{E}{(1+v)} \left[\frac{-u_0}{a} \right] = T$$

$$u_0 = -aT / \frac{E}{(1+v)}$$

Now substitute for u_0 in the general expression for σ_{rr} on previous page

$$\underline{\sigma_{rr}} = \frac{E}{(1+v)} \left[\frac{\left(aT/\frac{E}{(1+v)}\right)a}{r^2} \right] = T\left(\frac{a}{r}\right)^2$$

$$\underline{\sigma_{\theta\theta}} = -\sigma_{rr} = -T\left(\frac{a}{r}\right)^2$$



$$\underline{\sigma_{\theta\theta}} = -\sigma_{rr} = -T\left(\frac{a}{r}\right)^2$$

 Solution for in-plane displacements in terms of displacement boundary conditions <u>does not</u> depend on the elastic properties

$$u_r = (a/r)u_0$$
$$u_\theta = 0$$

 Solution for in-plane stresses in terms of traction (stress) boundary conditions <u>does not</u> depend on the elastic properties

$$\sigma_{\theta\theta} = -\sigma_{rr} = -T \left(\frac{a}{r}\right)^{2}$$

$$\sigma_{r\theta} = \sigma_{\theta r} = 0$$

- Solution for in-plane stresses in terms of displacement boundary conditions <u>does</u> depend on the elastic properties
- Solution for in-plane displacements in terms of traction (stress) boundary conditions <u>does</u> depend on the elastic properties

$$\sigma_{rr} = \frac{-E}{(1+v)} \left[\frac{u_0 a}{r^2} \right]$$


$$\sigma_{\theta\theta} = \frac{E}{(1+v)} \left[\frac{u_0 a}{r^2} \right]$$

$$u_r = \frac{-(1+v)}{E} \frac{a}{r} aT$$
$$u_\theta = 0$$

V Significance


For a *pressure* in a hole with no remote load at $r = \infty$:


- A The radial normal stress σ_{rr} is a principal stress because $\sigma_{r\theta} = 0$; σ_{rr} is the most compressive stress.
- B The circumferential normal stress $\sigma_{\theta\theta}$ is a principal stress because $\sigma_{\theta r} = 0$; $\sigma_{\theta\theta}$ is the most tensile stress.
- C A high pressure could cause radial cracking (e.g., radial dikes around a magma chamber).






VI Superposition







Pressure in a hole

Biaxial Tension (no hole)

$$\sigma_{rr} = -T(a/r)^2$$

$$\sigma_{\theta\theta} = -(-T)(a/r)^2$$

$$\sigma_{rr} = T$$

$$\sigma_{\theta\theta} = T$$

$$\sigma_{rr} = T - T(a/r)^{2}$$


$$\sigma_{\theta\theta} = T + T(a/r)^{2}$$

$$\sigma_{\theta\theta}|_{r=a} = 2T$$


Stress concentration!

VII Stress concentrations

- A The hole causes a <u>doubling</u> of the normal stress far from the hole (i.e., a <u>stress concentration)</u>
- B The magnitude of the circumferential stress at the hole is independent of the size of the hole, so a tiny cylindrical hole causes the same stress concentration as a large one.
- C A tiny hole near the wall of a larger hole might be expected to have an even larger stress concentration (why?)




Stress concentration!



VI Stress concentrations

- D Stress concentrations explain myriad phenomena, such as
 - 1 Why paper doesn't explode when pulled upon hard
 - Why paper tears along "the dotted line"
 - Why cracks in riveted steel plates start from the rivet holes
 - Why cracks in drying mudflats originate from the where grass stems have poked through the mud etc.
 - 5 Why "strong" rocks can fail under "low" stresses
 - Why dikes can propagate through the Earth's crust
 - 7 Why seismic ruptures grow so large



Stress concentration!

